

教育部 5G 行動寬頻人才培育跨校教學聯盟計畫
5G 行動網路協定與核網技術聯盟中心示範課程

4G/5G 行動寬頻協同網路

實驗三 SBA 建置與協定分析

副教授：吳俊興

助教：魏宏修

國立高雄大學 資訊工程學系


目錄

實驗三.....	0
一、 實驗架構.....	2
1. LTE 實驗架構	2
2. Free5GC 實驗架構	2
二、 軟硬體需求.....	3
1. 軟體.....	3
2. 硬體.....	3
三、 Free5GC 網路實驗平台建置.....	5
檢查.....	5
確認 Kernel 版本.....	5
0. 新增額外橋接 NIC(First).....	5
VM NIC Cards :.....	5
添加另一個具有橋接模式的網絡以連接到您的 eNodeB.....	5
1. MongoDB Golang Setup	7
安裝 MongoDB 3.6.3, Golang 1.11.4.	7
將配置文件寫入 TUN device。.....	9
如果 TUN device 禁用 IPv6，請從下面刪除 Address = cafe ::	
1/64。.....	9
檢查 Uptun 是否已啟動.....	10
安裝用於 source 的依賴項目	10
2. Free5gc Git clone 及編譯 開啟終端機(Terminal)輸入以下指令	11
確認安裝.....	11
3. 配置核心網絡並添加用戶信息.....	12
檢查 NIC 的環境.....	12
新增用戶信息.....	13
4. How to configure eNodeB..... 錯誤! 尚未定義書籤。	
Configure network interface of Core Network.... 錯誤! 尚未定義書	
籤。	
Configure eNodeB..... 錯誤! 尚未定義書籤。	
5. 重建 Project.....	14
6. 安裝並設定 OAI 的 eNB 軟體.....	15
7. 啟動 Free5GC.....	19
8. 啟動 eNB.....	22
9. 啟動 UE 端.....	23
Annex A : P 編程 SIM 卡	25


一、實驗架構

本實驗架構如下圖所示，共分成兩個部分，第一部分由 5GC 和 eNB 組成，透過程式指定 ip 位址由電腦開啟，而另一部分為 UE，使用手機進行訊號傳遞，形成 5G 基本網路架構。

1. LTE 實驗架構



2. Free5GC 實驗架構



二、軟硬體需求

1. 軟體

名稱	軟體	版本	目的
Free5GC	OS :	Ubuntu 18.04	啟動 HSS、 AMF、 SMF、 PCRF 和 UPF 功能
	Ubuntu	4.15.0-43-generic	
	Free5GC 的軟體	https://bitbucket.org/nctu_5g/free5gc.git	
	第三方擴充 套件: Gcc GO MongoDB		

2. 硬體

名稱	規格	數量	目的
5GC+eNB	桌上型電腦	2	啟動 HSS、 AMF、 SMF、 PCRF 和 UPF 功能
	USRP B210	1	
UE	ASUS_Z016D	1	

VM NIC Cards :

- NIC for connecting to the Internet :
- Network source: Virtual network - NAT
- Interface name in VM: ens33
- NIC for connecting to eNB :
- Network source: Host device <Host Interface Name>
- Interface name in VM: ens3

```
free5gc@ubuntu: ~
File Edit View Search Terminal Help
free5gc@ubuntu:~$ ifconfig
ens33: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet 192.168.72.255 netmask 255.255.255.0 broadcast 192.168.72.255
    inet6 fe80::5e61:564c:2715:7577 prefixlen 64 scopeid 0x20<link>
    ether 00:0c:29:95:93:f7 txqueuelen 1000 (Ethernet)
    RX packets 130 bytes 94429 (94.4 KB)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 188 bytes 45634 (45.6 KB)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0

ens38: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet 192.188.2.2 netmask 255.255.255.0 broadcast 192.188.2.255
    inet6 fe80::20c:29ff:fe95:9301 prefixlen 64 scopeid 0x20<link>
    inet6 2001:288:8003:208:20c:29ff:fe95:9301 prefixlen 64 scopeid 0x0<global>
    ether 00:0c:29:95:93:01 txqueuelen 1000 (Ethernet)
    RX packets 644 bytes 74103 (74.1 KB)
    RX errors 0 dropped 30 overruns 0 frame 0
    TX packets 65 bytes 9004 (9.0 KB)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0


lo: flags=73<UP,LOOPBACK,RUNNING> mtu 65536
    inet 127.0.0.1 netmask 255.0.0.0
    inet6 ::1 prefixlen 128 scopeid 0x10<host>
```

三、 Free5GC 網路實驗平台建置

檢查

確認 Kernel 版本

- `uname -a`




0. 新增額外橋接 NIC(First)

VM NIC Cards :


- 用於連接 Internet 的 NIC :
 - 網路來源 : Virtual network - NAT
 - 介面名稱 in VM : ens33
- 用於連接 eNB 的 NIC :
 - 網路來源 : Host device <Host Interface Name>
 - 介面名稱 in VM: ens38

添加另一個具有橋接模式的網絡以連接到您的 eNodeB


- 點選 Player -> Manage -> Virtual Machine Setting



- 選擇下方 Add 去選擇所需要的 Hardware Type
- 這邊我們選擇 Network Adapter



- 在 Network connection 選擇所需要的設定：Bridged
- 點選 Configure Adapters 確認連接網卡
- 確認完畢後即可點選 OK



1. MongoDB Golang Setup

安裝 MongoDB 3.6.3, Golang 1.11.4.

開啟一個終端機(Terminal)，並且依序輸入

- `sudo apt-get update`
- `sudo apt-get -y install mongodb wget git`
- `sudo systemctl start mongodb` (如果 `'/usr/bin/mongod'` 沒有運行)

```


free5gc@ubuntu:~$ sudo apt-get update
Get:1 http://security.ubuntu.com/ubuntu bionic-security InRelease [88.7 kB]
Hit:2 http://us.archive.ubuntu.com/ubuntu bionic InRelease
Hit:3 http://ppa.launchpad.net/freshark-dev/stable/ubuntu bionic InRelease
Get:4 http://us.archive.ubuntu.com/ubuntu bionic-updates InRelease [88.7 kB]
Get:5 http://security.ubuntu.com/ubuntu bionic-security/main amd64 Packages [451 kB]
Get:6 http://us.archive.ubuntu.com/ubuntu bionic-backports InRelease [74.6 kB]
Get:7 http://us.archive.ubuntu.com/ubuntu bionic-updates/main i386 Packages [559 kB]
Get:8 http://security.ubuntu.com/ubuntu bionic-security/main i386 Packages [340 kB]
Get:9 http://us.archive.ubuntu.com/ubuntu bionic-updates/main amd64 Packages [682 kB]
Get:10 http://security.ubuntu.com/ubuntu bionic-security/main amd64 DEP-11 Metadata [24.2 kB]
Get:11 http://security.ubuntu.com/ubuntu bionic-security/main DEP-11 48x48 Icons [10.4 kB]
Get:12 http://security.ubuntu.com/ubuntu bionic-security/main DEP-11 64x64 Icons [31.7 kB]
Get:13 http://security.ubuntu.com/ubuntu bionic-security/universe amd64 Packages [572 kB]
Get:14 http://us.archive.ubuntu.com/ubuntu bionic-updates/main amd64 DEP-11 Metadata [283 kB]
Get:15 http://us.archive.ubuntu.com/ubuntu bionic-updates/main DEP-11 48x48 Icons [66.7 kB]
Get:16 http://security.ubuntu.com/ubuntu bionic-security/universe i386 Packages [565 kB]
Get:17 http://us.archive.ubuntu.com/ubuntu bionic-updates/main DEP-11 64x64 Icons [138 kB]
Get:18 http://us.archive.ubuntu.com/ubuntu bionic-updates/universe amd64 Packages [972 kB]
Get:19 http://security.ubuntu.com/ubuntu bionic-security/universe amd64 DEP-11 Metadata [41.3 kB]
Get:20 http://security.ubuntu.com/ubuntu bionic-security/universe DEP-11 48x48 Icons [16.4 kB]
Get:21 http://security.ubuntu.com/ubuntu bionic-security/universe DEP-11 64x64 Icons [111 kB]
Get:22 http://security.ubuntu.com/ubuntu bionic-security/multiverse amd64 DEP-11 Metadata [2,464 B]
Get:23 http://us.archive.ubuntu.com/ubuntu bionic-updates/universe i386 Packages [955 kB]
Get:24 http://us.archive.ubuntu.com/ubuntu bionic-updates/universe Translation-en [294 kB]
Get:25 http://us.archive.ubuntu.com/ubuntu bionic-updates/universe amd64 DEP-11 Metadata [249 kB]
Get:26 http://us.archive.ubuntu.com/ubuntu bionic-updates/universe DEP-11 48x48 Icons [195 kB]
Get:27 http://us.archive.ubuntu.com/ubuntu bionic-updates/universe DEP-11 64x64 Icons [419 kB]
Get:28 http://us.archive.ubuntu.com/ubuntu bionic-updates/multiverse amd64 DEP-11 Metadata [2,468 B]
Get:29 http://us.archive.ubuntu.com/ubuntu bionic-backports/universe amd64 DEP-11 Metadata [7,224 B]
Fetched 7,240 kB in 14s (513 kB/s)
Reading package lists... Done
free5gc@ubuntu:~$ sudo apt-get -y install mongodb wget git
Reading package lists... Done
Building dependency tree
Reading state information... Done
git is already the newest version (1:2.17.1-1ubuntu0.4).
wget is already the newest version (1.19.4-1ubuntu2.2).
mongodb is already the newest version (3.6.3-0ubuntu1.1).
The following packages were automatically installed and are no longer required:
  amd64-microcode intel-microcode lucode-tool libmongoc-1.0-0 libsappy-dev
  thermal
Use 'sudo apt autoremove' to remove them.
0 upgraded, 0 newly installed, 0 to remove and 51 not upgraded.
free5gc@ubuntu:~$ sudo systemctl start mongod

```

檢查是否 golang 已經安裝

開啟終端機(Terminal)輸入以下指令

- go version




```
free5gc@ubuntu: ~
File Edit View Search Terminal Help
free5gc@ubuntu:~$ go version
go version go1.10.4 linux/amd64
free5gc@ubuntu:~$
```

如果沒有安裝，執行以下指令

開啟終端機(Terminal)輸入以下指令

- wget -q
https://storage.googleapis.com/golang/getgo/installer_ubuntu
- chmod +x installer_ubuntu
- ./installer_ubuntu
- source ~/.bash_profile
- rm -f installer_ubuntu



```
free5gc@ubuntu: ~
File Edit View Search Terminal Help
free5gc@ubuntu:~$ wget -q https://storage.googleapis.com/golang/getgo/installer_ubuntu
free5gc@ubuntu:~$ chmod +x installer_ubuntu
free5gc@ubuntu:~$ ./installer_ubuntu
Welcome to the Go installer!
Downloading Go version go1.12.7 to /home/free5gc/.go
This may take a bit of time...
Downloaded!
Setting up GOPATH
GOPATH has been set up!

One more thing! Run `source /home/free5gc/.bash_profile` to persist the
new environment variables to your current session, or open a
new shell prompt.
free5gc@ubuntu:~$ source ~/.bash_profile
free5gc@ubuntu:~$ rm -f installer_ubuntu
free5gc@ubuntu:~$
```

- go get -u -v "github.com/gorilla/mux"
- go get -u -v "golang.org/x/net/http2"
- go get -u -v "golang.org/x/sys/unix"

```
free5gc@ubuntu: ~
File Edit View Search Terminal Help
free5gc@ubuntu:~$ wget -q https://storage.googleapis.com/golang/getgo/installer_linux
free5gc@ubuntu:~$ chmod +x installer_linux
free5gc@ubuntu:~$ ./installer_linux
Welcome to the Go installer!
Downloading Go version go1.12.7 to /home/free5gc/.go
This may take a bit of time...
Downloaded!
Setting up GOPATH
GOPATH has been set up!

One more thing! Run `source /home/free5gc/.bash_profile` to persist the
new environment variables to your current session, or open a
new shell prompt.
free5gc@ubuntu:~$ source ~/.bash_profile
free5gc@ubuntu:~$ rm -f installer_linux
free5gc@ubuntu:~$ go get -u -v "github.com/gorilla/mux"
github.com/gorilla/mux (download)
free5gc@ubuntu:~$ go get -u -v "golang.org/x/net/http2"
Fetching https://golang.org/x/net/http2?go-get=1
Parsing meta tags from https://golang.org/x/net/http2?go-get=1
(status code 200)
```

將配置文件寫入 TUN device。

開啟終端機(Terminal)輸入以下指令

- `sudo sh -c "cat << EOF > /etc/systemd/network/99-free5gc.netdev`
- `[NetDev]`
- `Name=uptun`
- `Kind=tun`
- `EOF"`
- `sudo systemctl enable systemd-networkd`
- `sudo systemctl restart systemd-networkd`

```
free5gc@ubuntu: ~
File Edit View Search Terminal Help
free5gc@ubuntu:~$ sudo sh -c "cat << EOF > /etc/systemd/network/99-free5gc.netdev
> [NetDev]
> Name=uptun
> Kind=tun
> EOF"
[sudo] password for free5gc:
free5gc@ubuntu:~$ sudo systemctl enable systemd-networkd
free5gc@ubuntu:~$ sudo systemctl restart systemd-networkd
free5gc@ubuntu:~$
```

如果 TUN device 禁用 IPv6，請從下面刪除 `Address = cafe :: 1/64`。

- `sudo sh -c "cat << EOF > /etc/systemd/network/99-free5gc.network`
- `[Match]`
- `Name=uptun`

- [Network]
- Address=45.45.0.1/16
- Address=cafe::1/64
- EOF"
- sudo systemctl enable systemd-networkd
- sudo systemctl restart systemd-networkd

```

free5gc@ubuntu: ~
File Edit View Search Terminal Help
free5gc@ubuntu:~$ sudo sh -c "cat << EOF > /etc/systemd/network/99-free5gc.network
> [Match]
> Name=uptun
> [Network]
> Address=45.45.0.1/16
> Address=cafe::1/64
> EOF"
[sudo] password for free5gc:
free5gc@ubuntu:~$ sudo systemctl enable systemd-networkd
free5gc@ubuntu:~$ sudo systemctl restart systemd-networkd

```

檢查 Uptun 是否已啟動

- sudo apt-get install net-tools

```

free5gc@ubuntu: ~
File Edit View Search Terminal Help
free5gc@ubuntu:~$ sudo apt-get install net-tools
[sudo] password for free5gc:
Reading package lists... Done
Building dependency tree
Reading state information... Done
net-tools is already the newest version (1.60+git20161116.90da8a0-1ubuntu1).
The following packages were automatically installed and are no longer required:
  amd64-microcode intel-microcode iucode-tool libmongoc-1.0-0 libsappy-dev
  thermald
Use 'sudo apt autoremove' to remove them.
0 upgraded, 0 newly installed, 0 to remove and 51 not upgraded.
free5gc@ubuntu:~$

```

安裝用於 source 的依賴項目

- sudo apt-get -y install autoconf libtool gcc pkg-config git flex bison libsctp-dev libgnutls28-dev libcrypt-dev libssl-dev libidn11-dev libmongoc-dev libbson-dev libyaml-dev

```


free5gc@ubuntu: ~
File Edit View Search Terminal Help
free5gc@ubuntu:~$ sudo apt-get -y install autoconf libtool gcc pkg-config git fl
ex bison libsctp-dev libgnutls28-dev libcrypt-dev libssl-dev libidn11-dev libmo
ngoc-dev libbson-dev libyaml-dev

```

2. Free5gc Git clone 及編譯

開啟終端機(Terminal)輸入以下指令


- `git clone https://bitbucket.org/nctu_5g/free5gc.git`
- `cd free5gc`
- `autoreconf -iv`
- `./configure --prefix='pwd' /install`
- `make -j 'nproc'`
- `make install`



```
free5gc@ubuntu: ~/free5gc
File Edit View Search Terminal Help
free5gc@ubuntu:~$ git clone https://bitbucket.org/nctu_5g/free5gc.git
free5gc@ubuntu:~$ cd free5gc
free5gc@ubuntu:~/free5gc$ autoreconf -iv
free5gc@ubuntu:~/free5gc$ ./configure --prefix='pwd' /install
free5gc@ubuntu:~/free5gc$ make -j 'nproc'
free5gc@ubuntu:~/free5gc$ make install
```

確認安裝

- `./test/testngc -f`
`install/etc/free5gc/test/free5gc.testngc.conf`



```
free5gc@ubuntu: ~/free5gc
File Edit View Search Terminal Help
free5gc@ubuntu:~/free5gc$ ./test/testngc -f install/etc/free5gc/test/free5gc.testngc.conf
File Logging : '/home/free5gc/free5gc/install/var/log/free5gc/free5gc.log'
MongoDB URI : 'mongodb://localhost/free5gc'
Configuration : 'install/etc/free5gc/test/free5gc.testngc.conf'
s1ap_message_test : SUCCESS
nas_message_test : SUCCESS
gtp_message_test : SUCCESS
security_test : SUCCESS
s1setup_test : SUCCESS
attach_test : SUCCESS
ngsetup_test : SUCCESS
All tests passed.
Freeing memory...
free5gc@ubuntu:~/free5gc$
```

(發生問題&解決方法)

※請先確認是否連接網路正常。

※查詢前面 MongoDB, Golang 是否有成功啟動/安裝。

3. 配置核心網絡並添加用戶信息

檢查NIC的環境

#用於連接 Internet 的 NIC :

- ens33


#用於連接 eNB 的 NIC :

- ens38

使用指令確認對內網卡及對外網卡

開啟終端機(Terminal)輸入以下指令


- ifconfig



```
free5gc@ubuntu: ~
File Edit View Search Terminal Help
free5gc@ubuntu:~$ ifconfig
ens33: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet 192.168.72.128 netmask 255.255.255.0 broadcast 192.168.72.255
    inet6 fe80::5e61:564c:2715:7577 prefixlen 64 scopeid 0x20<link>
    ether 00:0c:29:95:93:f7 txqueuelen 1000 (Ethernet)
    RX packets 138321 bytes 28477083 (28.4 MB)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 73615 bytes 11944247 (11.9 MB)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0

ens38: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet 192.188.2.2 netmask 255.255.255.0 broadcast 192.188.2.255
```

- sudo ifconfig ens38 192.188.2.2
- cd free5gc/webui/
- sudo apt install npm
- npm install
- npm run dev



```
free5gc@ubuntu: ~/free5gc/webui
File Edit View Search Terminal Help
free5gc@ubuntu:~/free5gc/webui$ npm run dev
> nextepc@0.3.9 dev /home/free5gc/free5gc/webui
> node server/index.js

> Using external babel configuration
> Location: "/home/free5gc/free5gc/webui/.babelrc"

[DONE] Compiled successfully in 5736ms 11:02:23 AM

Mongoose: accounts.count({}, {})
> Ready on http://localhost:3000
Mongoose: subscribers.ensureIndex({ imsi: 1 }, { unique: true, background: true })
Mongoose: accounts.ensureIndex({ username: 1 }, { unique: true, background: true })
```

新增用戶信息

- 在網頁上輸入網址 <http://localhost:3000>
- 點選右下 ⊕ 進行新增動作
- 輸入使用者帳號密碼
 - Username : admin
 - Password : 1423
- 新增用戶資訊的 IMSI, K, OPc

■ USIM 資訊 (在這個例子)

```
- IMSI 208930000000003
- K 8baf473f2f8fd09487cccbd7097c6862
- OPc 8e27b6af0e692e750f32667a3b14605d
```

- Save

free5GC

Edit Subscriber

Subscriber Configuration

IMSI*

208930000000003

Subscriber Key (K)*

8baf473f2f8fd09487cccbd7097c6862

Authentication Management Field (AMF)*

8000

USIM Type

OPc

Operator Key (OPc/OP)*

8e27b6af0e692e750f32667a3b14605d

UE-AMBR Downlink (Kbps)*

1024000

UE-AMBR Uplink (Kbps)*

1024000

APN Configurations

Access Point Name (APN)*

CANCEL SAVE

(發生問題&解決方法)

查詢 `npm install` 是否安裝正確，`npm` 套件可能在安裝中打結。

4. 重建 Project

- (Control-C kill free5gc-ngcd)
- make maintainer-clean
- rm -rf ./install
- git pull
- autoreconf -iv
- ./configure --prefix='pwd' /install
- make -j 'nproc'
- make install
- ./free5gc-ngcd

5. 安裝並設定 OAI 的 eNB 軟體

安裝 Ubuntu 14.04(ubuntu-14.04.4-desktop-amd64)

- 安裝時選擇英文。

開啟終端機輸入以下指令將更新所有已安裝套件。

- `sudo apt-get update`
- `sudo apt-get upgrade`

在 eNB 上開啟一個新的終端機，並且輸入

- `sudo apt-get install linux-image-3.19.0-61-lowlatency linux-headers-3.19.0-61-lowlatency`
- `sudo apt-get install cpufrequtils`
- `sudo apt-get install i7z`

修改開機選單和設定

在終端機輸入以下指令

- `sudo gedit /etc/default/grub`

"GRUB_HIDDEN_TIMEOUT=0" 改成 "#GRUB_HIDDEN_TIMEOUT=60"

然後把

`GRUB_CMDLINE_LINUX_DEFAULT = ""`

改成

`GRUB_CMDLINE_LINUX_DEFAULT="quiet intel_pstate=distable
processor.max_cstate=1 intel_idle.max_cstate=0 idle=poll"`

在終端機輸入以下指令

- `sudo gedit /etc/default/cpufrequtils`

新增以下這行指令

`GOVERNOR="performance"`

然後儲存並關閉

在終端機輸入以下指令

- `sudo update-grub2`
- `sudo update-rc.d ondemand disable`

然後終端機輸入以下指令，重啟電腦

- `sudo reboot`

下載 git 套件並取得認證

開啟一個新的終端機，並且輸入

- `sudo apt-get install subversion git`
- `git config --global user.name "輸入你的名稱"`
- `git config --global user.email "輸入你的電子信箱"`
- `sudo su`
- `echo -n | openssl s_client -showcerts -connect gitlab.eurecom.fr:443 2>/dev/null | sed -ne '/-BEGIN CERTIFICATE-/,/-END CERTIFICATE-/p' >> /etc/ssl/certs/ca-certificates.crt`
- `exit`

請先前往 Gitlab 註冊

如果這一頁的指令執行正確，終端機是不會有任何訊息產生

下載源始碼並安裝 OAI eNB 軟體所需的套件

在終端機輸入

- `git clone https://gitlab.eurecom.fr/oai/openairinterface5g.git`

在終端機輸入以下指令來下載並安裝 OAI eNB 軟體所需的套件

- `cd ~/openairinterface5g`
- `source oaienv`
- `cd cmake_targets`
- `./build_oai -l --eNB -x --install-system-files -w USRP --install-optional-packages`

修改 eNB 的設定檔

在終端機輸入

- `gedit ~/openairinterface5g/targets/PROJECTS/GENERIC-LTE-EPC/CONF/enb.band39.tm1.usrpb210.conf`

或

- `gedit ~/openairinterface5g/targets/PROJECTS/GENERIC-LTE-EPC/CONF/enb.band7.tm1.usrpb210.conf`

在 “~/openairinterface5g/targets/PROJECTS/GENERIC-LTE-EPC/CONF/” 目錄下有很多種 eNB 的設定檔，當 eNB 啟動時會載入這些設定檔，有需要的話可以修改訊號頻率，這裡是使用 Band 39 和 Band 7

修改以下設定

- tracking_area_code = "1";
- mobile_country_code = "208";
- mobile_network_code = "93";

設定 mobile_country_code、mobile_network_code、tracking_area_code 這三個部分，須確定跟 EPC 的資料庫及 SIM 卡中的 MCC、MNC、TAC 這三部分對應

設定 eNB 所連接的 5GC 的 IP 位址

```
140
141
142 // MME parameters:
143 mme_ip_address = ( { ipv4 = "192.188.2.2";
144                    ipv6 = "192:168:30::17";
145                    active = "yes";
146                    preference = "ipv4";
147                    }
148 );
149
150 NETWORK_INTERFACES :
151 {
152   ENB_INTERFACE_NAME_FOR_S1_MME = "enp0s31f6";
153   ENB_IPV4_ADDRESS_FOR_S1_MME = "192.188.2.253/24";
154   ENB_INTERFACE_NAME_FOR_S1U = "enp0s31f6";
155   ENB_IPV4_ADDRESS_FOR_S1U = "192.188.2.253/24";
156   ENB_PORT_FOR_S1U = 2152; # Spec 2152
157 }
158
```

解釋：

設定 eNB 所連接的 EPC 的 IP 位址

ipv4 = "EPC 對內網卡的 IP"

ENB_INTERFACE_NAME_FOR_S1_MME = "eNB 的網卡名稱"

ENB_IPV4_ADDRESS_FOR_S1_MME = "eNB 的網卡 IP"

ENB_INTERFACE_NAME_FOR_S1U = "eNB 的網卡名稱"

ENB_IPV4_ADDRESS_FOR_S1U = "eNB 的網卡 IP"

重新編譯 eNB

在終端機輸入

- cd ~/openairinterface5g
- source oaienv
- ./cmake_targets/build_oai -w USRP -x -c -eNB
- cd cmake_targets/lte_build_oai/build

(發生問題&解決方法)

- 檢查 CPU 的效能設定
 - (在終端機輸入)
 - sudo i7z (確認 CPU 頻率)
 - cpufreq-info

(CPU Frequency Scaling 從 Powersave 模式變為 Performance 模式)

- 確認 Kernel 版本
 - `uname -a`

```
enb@enb:~  
Cpu speed from cpufreq 3591.00MHz  
cpufreq might be wrong if cpufreq is enabled. To guess correctly try estimating  
Linux's inbuilt cpu_khz code emulated now  
True Frequency (without accounting Turbo) 3591 MHz  
CPU Multiplier 36x || Bus clock frequency (BCLK) 99.75 MHz  
  
Socket [0] - [physical cores=4, logical cores=8, max online cores ever=4]  
TURBO ENABLED on 4 Cores, Hyper Threading ON  
Max Frequency without considering Turbo 3690.75 MHz (99.75 x [37])  
Max TURBO Multiplier (if Enabled) with 1/2/3/4 Cores is 40x/40x/39x/38x  
Real Current Frequency 3790.40 MHz [99.75 x 38.00] (Max of below)  
Core [core-id] :Actual Freq (Mult.) C0% Halt(C1)% C3 % C6 %  
Core 1 [0]: 3790.40 (38.00x) 100 0 0 0  
Core 2 [1]: 3790.40 (38.00x) 100 0 0 0  
Core 3 [2]: 3790.40 (38.00x) 100 0 0 0  
Core 4 [3]: 3790.40 (38.00x) 100 0 0 0  
  
C0 = Processor running without halting  
C1 = Processor running with halts (States >C0 are power saver)  
C3 = Cores running with PLL turned off and core cache turned off  
C6 = Everything in C3 + core state saved to last level cache  
Above values in table are in percentage over the last 1 sec
```

```
enb@enb:~$ cpufreq-info  
cpufrequtils 008: cpufreq-info (C) Dominik Brodowski 2004-2009  
Report errors and bugs to cpufreq@vger.kernel.org, please.  
analyzing CPU 0:  
driver: intel_pstate  
CPUs which run at the same hardware frequency: 0  
CPUs which need to have their frequency coordinated by software: 0  
maximum transition latency: 0.97 ms.  
hardware limits: 800 MHz - 4.00 GHz  
available cpufreq governors: performance, powersave  
current policy: frequency should be within 800 MHz and 4.00 GHz.  
The governor "performance" may decide which speed to use  
within this range.  
current CPU frequency is 3.80 GHz.
```

```
enb@enb:~$ uname -a  
Linux enb 3.19.0-61-lowlatency #69~14.04.1-Ubuntu SMP  
enb@enb:~$
```

6. 啟動 Free5GC


srsLTE 執行順序為 5GC->eNB->UE，USRP-B210 需用 USB 3.0 接口，若是使用 USB 2.0 可能會導致無法讀取。

在本實驗中 5GC 跟 eNB 是使用同一台電腦執行，UE 則是使用手機。

6.1 HSS

開啟終端機(Terminal)輸入以下指令

- `cd free5gc`
- `./nextepc-hssd`



```
free5gc@ubuntu: ~/free5gc
File Edit View Search Terminal Help
free5gc@ubuntu:~$ cd free5gc
free5gc@ubuntu:~/free5gc$ ./next-hssd
bash: ./next-hssd: No such file or directory
free5gc@ubuntu:~/free5gc$ ./nextepc-hssd
free5GC daemon v1.0.0 - Jul 17 2019 00:12:06

PID[87364] : '/home/free5gc/free5gc/install/var/run/nextepc-hssd/pid'
File Logging : '/home/free5gc/free5gc/install/var/log/free5gc/free5gc.log'
MongoDB URI : 'mongodb://localhost/free5gc'
Configuration : '/home/free5gc/free5gc/install/etc/free5gc/free5gc.conf'
[07/22 23:29:48.305] HSS try to initialize
[07/22 23:29:48.369] HSS initialize...done

[07/22 23:29:48.369] INFO: free5GC daemon start (main.c:157)
^C[07/22 23:30:13.880] INFO: SIGINT received (main.c:50)
[07/22 23:30:13.881] INFO: free5GC daemon terminating... (main.c:160)
[07/22 23:30:13.881] HSS try to terminate
[07/22 23:30:13.895] freeDiameter[6]: Initiating freeDiameter shutdown sequence (3)
[07/22 23:30:14.179] HSS terminate...done
[07/22 23:30:14.179] DB-Client try to terminate
[07/22 23:30:14.191] DB-Client terminate...done
free5gc@ubuntu:~/free5gc$ ./nextepc-hssd
free5GC daemon v1.0.0 - Jul 17 2019 00:12:06

PID[87425] : '/home/free5gc/free5gc/install/var/run/nextepc-hssd/pid'
File Logging : '/home/free5gc/free5gc/install/var/log/free5gc/free5gc.log'
MongoDB URI : 'mongodb://localhost/free5gc'
Configuration : '/home/free5gc/free5gc/install/etc/free5gc/free5gc.conf'
[07/22 23:30:19.309] HSS try to initialize
[07/22 23:30:19.356] HSS initialize...done

[07/22 23:30:19.356] INFO: free5GC daemon start (main.c:157)
[07/22 23:30:52.061] INFO: CONNECTED TO 'amf.localdomain' (TCP,soc#8): (fd_logger.c:93)
```

6.2 AMF

開啟終端機(Terminal)輸入以下指令

- `cd free5gc`
- `./free5gc-amfd`

```

free5gc@ubuntu: ~/free5gc
File Edit View Search Terminal Help
free5gc@ubuntu:~$ cd free5gc
free5gc@ubuntu:~/free5gc$ ./free5gc-amfd
free5GC daemon v1.0.0 - Jul 17 2019 00:12:06

PID[87465] : '/home/free5gc/free5gc/install/var/run/free5gc-amfd/pid'
File Logging : '/home/free5gc/free5gc/install/var/log/free5gc/free5gc.log'
MongoDB URI : 'mongodb://localhost/free5gc'
Configuration : '/home/free5gc/free5gc/install/etc/free5gc/free5gc.conf'
[07/22 23:30:50.126] AMF try to initialize
[07/22 23:30:52.002] AMF initialize...done

[07/22 23:30:52.002] INFO: free5GC daemon start (main.c:157)
[07/22 23:30:52.008] sip_server() [192.188.2.2]:36412
[07/22 23:30:52.080] INFO: CONNECTED TO 'hss.localdomain' (TCP,soc#10): (fd_logger.c:93)
[07/23 06:30:56.001] AM4G overload_start (load_avg/n_cores=2.34, threshold=0.80)
[07/23 06:35:44.900] AMF4G overload_stop (load_avg/n_cores=0.76, threshold=0.80)
[07/23 07:02:40.429] AM4G overload_start (load_avg/n_cores=1.12, threshold=0.80)
[07/23 07:05:13.082] AMF4G overload_stop (load_avg/n_cores=0.73, threshold=0.80)
[07/23 18:29:50.165] AM4G overload_start (load_avg/n_cores=1.05, threshold=0.80)
[07/23 18:31:12.941] AMF4G overload_stop (load_avg/n_cores=0.68, threshold=0.80)
[07/24 05:26:14.151] AM4G overload_start (load_avg/n_cores=2.48, threshold=0.80)
[07/24 05:30:33.873] AMF4G overload_stop (load_avg/n_cores=0.80, threshold=0.80)
[07/24 05:57:31.262] AM4G overload_start (load_avg/n_cores=1.45, threshold=0.80)
[07/24 05:58:43.459] AMF4G overload_stop (load_avg/n_cores=0.74, threshold=0.80)
[07/24 06:28:20.411] AM4G overload_start (load_avg/n_cores=1.64, threshold=0.80)
[07/24 06:30:21.532] AMF4G overload_stop (load_avg/n_cores=0.79, threshold=0.80)
[07/24 07:30:37.785] AM4G overload_start (load_avg/n_cores=0.90, threshold=0.80)
[07/24 07:31:27.969] AMF4G overload_stop (load_avg/n_cores=0.77, threshold=0.80)
[07/24 08:01:11.528] AM4G overload_start (load_avg/n_cores=0.99, threshold=0.80)
[07/24 08:01:41.589] AMF4G overload_stop (load_avg/n_cores=0.73, threshold=0.80)
[07/24 08:31:48.005] AM4G overload_start (load_avg/n_cores=0.81, threshold=0.80)
[07/24 08:32:52.316] AMF4G overload_stop (load_avg/n_cores=0.68, threshold=0.80)
[07/24 09:03:00.526] AM4G overload_start (load_avg/n_cores=0.87, threshold=0.80)
[07/24 09:04:14.193] AMF4G overload_stop (load_avg/n_cores=0.76, threshold=0.80)
[07/24 09:34:22.002] AM4G overload_start (load_avg/n_cores=1.14, threshold=0.80)
[07/24 09:34:52.100] AMF4G overload_stop (load_avg/n_cores=0.69, threshold=0.80)
[07/24 10:04:45.318] AM4G overload_start (load_avg/n_cores=1.13, threshold=0.80)
[07/24 10:05:25.824] AMF4G overload_stop (load_avg/n_cores=0.68, threshold=0.80)

```

6.3 SMF

開啟終端機(Terminal)輸入以下指令

- cd free5gc
- ./free5gc-smfd

```

free5gc@ubuntu: ~/free5gc
File Edit View Search Terminal Help
free5gc@ubuntu:~$ cd free5gc
free5gc@ubuntu:~/free5gc$ ./free5gc-smfd
free5GC daemon v1.0.0 - Jul 17 2019 00:12:06

PID[87539] : '/home/free5gc/free5gc/install/var/run/free5gc-smfd/pid'
File Logging : '/home/free5gc/free5gc/install/var/log/free5gc/free5gc.log'
MongoDB URI : 'mongodb://localhost/free5gc'
Configuration : '/home/free5gc/free5gc/install/etc/free5gc/free5gc.conf'
[07/22 23:31:20.703] SMF try to initialize
[07/22 23:31:21.080] pfcf_server() [127.0.0.2]:8805
[07/22 23:31:21.080] pfcf_connect() [192.188.2.2]:8805
[07/22 23:31:21.080] pfcf_xact_local_create 1 not freed in pfcf_xact_pool[64] of PFCF Transaction
[07/22 23:31:21.080] SMF initialize...done

[07/22 23:31:21.081] INFO: free5GC daemon start (main.c:157)
[07/22 23:31:21.083] ERRR: corek_rcvfrom(len:8192) failed(111:Connection refused) (unix/socket.c:635)
[07/22 23:31:21.083] WARN: corek_rcv failed(111:Connection refused) (pfcf_path.c:208)
[07/22 23:31:24.086] ERRR: corek_rcvfrom(len:8192) failed(111:Connection refused) (unix/socket.c:635)
[07/22 23:31:24.087] WARN: corek_rcv failed(111:Connection refused) (pfcf_path.c:208)
[07/22 23:31:27.097] ERRR: corek_rcvfrom(len:8192) failed(111:Connection refused) (unix/socket.c:635)
[07/22 23:31:27.098] WARN: corek_rcv failed(111:Connection refused) (pfcf_path.c:208)
[07/22 23:31:30.104] WARN: [1] LOCAL No Reponse. Give up! for step 1 type 5 peer [192.188.2.2]:8805 (pfcf_xact.c:671)
[07/22 23:31:57.911] INFO: CONNECTED TO 'pcrf.localdomain' (TCP,soc#9): (fd_logger.c:93)
[07/24 05:27:32.382] ERRR: DROPPED 'Answer received with no corresponding sent request' (fd_logger.c:93)

```

6.4 PCRF

開啟終端機(Terminal)輸入以下指令

- cd free5gc
- ./nextepc-pcrfd

```
free5gc@ubuntu: ~/free5gc
File Edit View Search Terminal Help
free5gc@ubuntu:~$ cd free5gc
free5gc@ubuntu:~/free5gc$ ./nextepc-pcrfd
free5GC daemon v1.0.0 - Jul 17 2019 00:12:06

PID[87607] : '/home/free5gc/free5gc/install/var/run/nextepc-pcrfd/pid'
File Logging : '/home/free5gc/free5gc/install/var/log/free5gc/free5gc.log'
MongoDB URI : 'mongodb://localhost/free5gc'
Configuration : '/home/free5gc/free5gc/install/etc/free5gc/free5gc.conf'
[07/22 23:31:57.884] PCRF try to initialize
[07/22 23:31:57.910] PCRF initialize...done

[07/22 23:31:57.910] INFO: free5GC daemon start (main.c:157)
[07/22 23:31:57.912] INFO: CONNECTED TO 'smf.localdomain' (TCP,soc#10): (fd_logger.c:93)
[07/24 05:27:32.451] ERROR: DROPPED 'Answer received with no corresponding sent request.' (fd_
_init.c:116)
[07/24 05:27:35.846] ERROR: 'Device-Watchdog-Answer' (fd_init.c:116)
[07/24 05:27:35.846] ERROR: Version: 0x01 (fd_init.c:116)
[07/24 05:27:35.846] ERROR: Length: 88 (fd_init.c:116)
[07/24 05:27:35.846] ERROR: Flags: 0x00 (----) (fd_init.c:116)
[07/24 05:27:35.846] ERROR: Command Code: 280 (fd_init.c:116)
[07/24 05:27:35.846] ERROR: ApplicationId: 0 (fd_init.c:116)
[07/24 05:27:35.846] ERROR: Hop-by-Hop Identifier: 0x1A73F796 (fd_init.c:116)
[07/24 05:27:35.846] ERROR: End-to-End Identifier: 0x90DD28FD (fd_init.c:116)
[07/24 05:27:35.846] ERROR: {internal data}; src:smf.localdomain(15) rwb:(nil) rt:0 c
p:(nil),(nil)((nil)) qry:(nil) asso:0 sess:(nil) (fd_init.c:116)
[07/24 05:27:35.846] ERROR: AVP: 'Result-Code'(268) l=12 f=-M val='DIAMETER_SUCCESS'
(2001 (0x7d1)) (fd_init.c:116)
[07/24 05:27:35.846] ERROR: AVP: 'Origin-Host'(264) l=23 f=-M val='smf.localdomain' (
fd_init.c:116)
[07/24 05:27:35.846] ERROR: AVP: 'Origin-Realm'(296) l=19 f=-M val='localdomain' (fd_
_init.c:116)
[07/24 05:27:35.846] ERROR: AVP: 'Origin-State-Id'(278) l=12 f=-M val='1563863481 (0x5
d36a9b9)' (fd_init.c:116)
[07/24 05:29:03.004] INFO: CONNECTED TO 'smf.localdomain' (TCP,soc#9): (fd_logger.c:93)
```

6.5 UPF

開啟終端機(Terminal)輸入以下指令

- cd free5gc
- ./free5gc-upfd

```
free5gc@ubuntu: ~/free5gc
File Edit View Search Terminal Help
free5gc@ubuntu:~$ cd free5gc
free5gc@ubuntu:~/free5gc$ ./free5gc-upfd
free5GC daemon v1.0.0 - Jul 17 2019 00:12:06

PID[87676] : '/home/free5gc/free5gc/install/var/run/free5gc-upfd/pid'
File Logging : '/home/free5gc/free5gc/install/var/log/free5gc/free5gc.log'
MongoDB URI : 'mongodb://localhost/free5gc'
Configuration : '/home/free5gc/free5gc/install/etc/free5gc/free5gc.conf'
[07/22 23:32:46.445] UPF try to initialize
[07/22 23:32:47.049] UPF initialize...done

[07/22 23:32:47.050] INFO: free5GC daemon start (main.c:157)
```

7. 啟動 eNB

在另一台電腦的終端機輸入以下其中一個指令，選擇不同的 Band

- `sudo -E ./lte-softmodem -O $OPENAIR_DIR/targets/PROJECTS/GENERIC-LTE-EPC/CONF/enb.band39.tm1.usrpb210.conf -d`

```
enb@D830MT: ~/openairinterfaceSg/cmake_targets/lte_build_oai/build
[ LWIP][I] de68 00 12 0 0 0.00 0.00 0.00
Received SIGINT
closing all tasks
^C[UDP][W]Received TERMINATE_MESSAGE
Exiting eNB_single thread
[ LWIP][I] de68 00 12 0 0 0.00 0.00 0.00
ready_tasks 0
waiting for XFORMS thread
stopping MODEM threads
Killing eNB 0 processing threads
Exiting eNB thread PRACH
enb@D830MT:~/openairinterfaceSg/cmake_targets/lte_build_oai/build$ sudo -E ./lte-softmodem -O $OPEN
AIR_DIR/targets/PROJECTS/GENERIC-LTE-EPC/CONF/enb.band39.tm1.usrpb210.conf -d
[sudo] password for enb:
# /dev/cpu_dna_latency set to 0us
log init done
Running with XFORMS!
num component carrier 1
WARNING: setting 'gtpu_log_level' not found in configuration file
WARNING: setting 'gtpu_log_verbosity' not found in configuration file
WARNING: setting 'udp_log_level' not found in configuration file
WARNING: setting 'udp_log_verbosity' not found in configuration file
WARNING: setting 'osa_log_level' not found in configuration file
WARNING: setting 'osa_log_verbosity' not found in configuration file

-----
ENB CONFIG FILE CONTENT LOADED (TBC):
-----
ENB CONFIG for instance 0:

eNB name:          eNB_Eurecom_LTEBox:
eNB ID:            3584:
Cell type:         CELL_MACRO_ENB:
TAC:               1:
MCC:               208:
MNC:               93:

node_function for CC 0:      eNodeB_3GPP:
node_timing for CC 0:        synch_to_ext_device:
node_synch_ref for CC 0:     0:
eutra_band for CC 0:         39:
downlink_freq for CC 0:      1910000000:
uplink_freq_offset for CC 0: 0:

Cell ID for CC 0:           0:
N_RB_DL for CC 0:           25:
nb_antennas_tx for CC 0:    1:
nb_antennas_rx for CC 0:    1:
rach_numberOFRA_Preambles for CC 0: 15:
rach_preamblesGroupAConfig for CC 0: 0:
rach_powerRampingStep for CC 0: 2:
```

8. 啟動 UE 端

此例的 SIM Card 資料是使用 Free5gc 官方所提供的 SIM Card 資料範例，可跟據自己的情況來燒錄 SIM Card 的資料

- IMSI : 208930000000003
- K : 8baf473f2f8fd09487cccbd7097c6862
- OPc : 8e27b6af0e692e750f32667a3b14605d
- MCC : 208 (FR)
- MNC : 93 (new MNO MNC)

設定 APN

- 名稱設為 eur
- APN 設為 oai.ipv4
- 承載系統為 LTE



注意

- 某些手機可能要關掉 VoLTE 通話
- 某些手機要設定只能使用 LTE
- 以上設置根據不同手機有不同的設置方法




手機主動搜尋基地台




Annex A : P 編程 SIM 卡

開啟終端機(Terminal)輸入以下指令


- `sudo apt-get update && sudo apt-get upgrade -y`
- `sudo apt-get install pcscd pcsc-tools libccid python-dev swig python-setuptools python-pip libpcsclite-dev -y`
- `pip install pycrypto`



```
free5gc@ubuntu: ~
File Edit View Search Terminal Help
free5gc@ubuntu:~$ sudo apt-get update && apt-get upgrade -y
```



```
free5gc@ubuntu: ~
File Edit View Search Terminal Help
free5gc@ubuntu:~$ sudo apt-get install pcscd pcsc-tools libccid python-dev swig
python-setuptools python-pip libpcsclite-dev -y
[sudo] password for free5gc:
Reading package lists... Done
Building dependency tree
Reading state information... Done
libpcsclite-dev is already the newest version (1.8.23-1).
python-dev is already the newest version (2.7.15-rc1-1).
python-setuptools is already the newest version (39.0.1-2).
libccid is already the newest version (1.4.29-1).
pcsc-tools is already the newest version (1.5.2-2).
pcscd is already the newest version (1.8.23-1).
swig is already the newest version (3.0.12-1).
```






```
free5gc@ubuntu: ~
File Edit View Search Terminal Help
free5gc@ubuntu:~$ pip install pycrypto
Collecting pycrypto
Installing collected packages: pycrypto
Successfully installed pycrypto-2.6.1
```

安裝 Pyscard

- 前往下方網址
- <https://sourceforge.net/projects/pyscard/files/pyscard/pyscard%201.9.5/pyscard-1.9.5.tar.gz/download>
- 解壓縮檔案在桌面

開啟終端機(Terminal)輸入以下指令

- `cd ~/Desktop/pyscard-1.9.5`
- `sudo python setup.py build_ext install`
- `cd ~`
- `git clone git://git.osmocom.org/pysim.git`



執行 Pysim 及 連接 SIM Card Reader

- cd pysim/
 - sudo pcsc_scan
- ctrl + C to exit the program
- ./pySim-read.py -p 0
 - ./pySim-prog.py -p 0 -x 208 -y 93 -t sysmoUSIM-SJS1 -i 208930000000003 -- op=8e27b6af0e692e750f32667a3b14605d -k 8baf473f2f8fd09487cccbd7097c6862 -s 8988211000000088313 -a 23605945

```
free5gc@ubuntu: ~/pysim
File Edit View Search Terminal Help
free5gc@ubuntu:~$ cd pysim
free5gc@ubuntu:~/pysim$ sudo pcsc_scan
[sudo] password for free5gc:
PC/SC device scanner
V 1.5.2 (c) 2001-2017, Ludovic Rousseau <ludovic.rousseau@free.fr>
Using reader plug'n play mechanism
Scanning present readers...
Waiting for the first reader... -
```

- 指令解釋：
 - -x = MCC
 - -y = MNC
 - -t = tag
 - -i = IMSI
 - --op = OP
 - -k = KI
 - -s = ICCID
 - -a = ADM1

```
free5gc@ubuntu: ~/pysim
File Edit View Search Terminal Help
free5gc@ubuntu:~/pysim$ sudo pcsc_scan
[sudo] password for free5gc:
PC/SC device scanner
V 1.5.2 (c) 2001-2017, Ludovic Rousseau <ludovic.rousseau@free.fr>
Using reader plug'n play mechanism
Scanning present readers...
Waiting for the first reader...found one
Scanning present readers...
0: VMware Virtual USB CCID 00 00

Thu Jul 25 04:42:45 2019
Reader 0: VMware Virtual USB CCID 00 00
Card state: Card inserted,
ATR: 3B 9F 95 80 1F C3 80 31 E0 73 FE 21 13 57 86 81 02 86 98 44 18 A8

ATR: 3B 9F 95 80 1F C3 80 31 E0 73 FE 21 13 57 86 81 02 86 98 44 18 A8
+ TS = 3B --> Direct Convention
+ T0 = 9F, Y(1): 1001, K: 15 (historical bytes)
TA(1) = 95 --> Fi=512, Di=16, 32 cycles/ETU
125000 bits/s at 4 MHz, fMax for Fi = 5 MHz => 156250 bits/s
TD(1) = 80 --> Y(i+1) = 1000, Protocol T = 0
-----
TD(2) = 1F --> Y(i+1) = 0001, Protocol T = 15 - Global interface bytes followi
ng
-----
TA(3) = C3 --> Clock stop: no preference - Class accepted by the card: (3G) A
5V B 3V
+ Historical bytes: 80 31 E0 73 FE 21 13 57 86 81 02 86 98 44 18
Category indicator byte: 80 (compact TLV data object)
Tag: 3, len: 1 (card service data byte)
Card service data byte: E0
- Application selection: by full DF name
- Application selection: by partial DF name
- BER-TLV data objects available in EF.DIR
- EF.DIR and EF.ATR access services: by GET RECORD(s) command
- Card with MF
Tag: 7, len: 3 (card capabilities)
Selection methods: FE
- DF selection by full DF name
- DF selection by partial DF name
- DF selection by path
- DF selection by file identifier
- Implicit DF selection
- Short EF identifier supported
```

```
free5gc@ubuntu: ~/pysim
File Edit View Search Terminal Help
- DF selection by path
- DF selection by file identifier
- Implicit DF selection
- Short EF identifier supported
- Record number supported
Data coding byte: 21
- Behaviour of write functions: proprietary
- Value 'FF' for the first byte of BER-TLV tag fields: invalid
- Data unit in quartets: 2
Command chaining, length fields and logical channels: 13
- Logical channel number assignment: by the card
- Maximum number of logical channels: 4
Tag: 5, len: 7 (card issuer's data)
Card issuer data: 86 81 02 86 98 44 18
+ TCK = A8 (correct checksum)

Possibly identified card (using /usr/share/pcsc/smartcard_list.txt):
3B 9F 95 80 1F C3 80 31 E0 73 FE 21 13 57 86 81 02 86 98 44 18 A8
GREEN CARD, Grcard (Hong Kong ) Co.,Limited, LTE Usim Card (Telecommuni
cation)
Celcom Postpaid 3G (Telecommunication)
/
```